


Networked Kisslicer Setup

Step 1:


PREREQUISITES:

- Ensure that the computer will remember these changes after a power cycle!
- Install the normal Windows installer package from Polyprinter, Downloads page on the website: https://www.polyprinter.com/content/PolyPrinterSetup_Win64.exe
- Download the Dx Slicing Setup (supports N) from the link:
<https://polyprinter.com/content/DXSlicingSetup.zip>


Step 2: Unzip the downloaded folder



Step 3: Copy all of the folders contents




Step 4: Enter the PRO registration code in KISSlicer. Then **close out** KISSlicer




Note: Every customer automatically has a PRO code. Please contact us if yours is currently unknown.

Step 5: Locate the KISSlicer settings folder



Note: The ProgramData folder is usually hidden in the C:/ . Simply go to the view tab and click the checkbox for Hidden Items

Step 6: Paste the contents copied from DX Slicing Setup into your KISSlicer folder



Note: If there are duplicates during pasting, replace all.

Everything should now be set up so that KISSlicer can support our Networked printers. Please review the DX Basic User Guide on our website if you have a DX printer.

When you launch KISSlicer, take a few seconds to do File, Enter Registration Key, in KISSlicer, if your organization has been given a key.